

**propellerhead**

**A-LIST ELECTRIC GUITARIST -  
POP CHORDS  
MIDI IMPLEMENTATION CHART**

# Electric Guitarist - Pop Chords MIDI Controller Chart

MIDI Contr. #	MIDI Controller Name	Acoustic Guitarist Parameter
0	ControlBankSelect	
1	ControlModulationWheel	
2	ControlBreathController	
3	ControlUndefined3	
4	ControlFootController	
5	ControlPortamentoTime	
6	ControlDataEntryMSB	
7	ControlChannelVolume	Volume
8	ControlBalance	
9	ControlUndefined9	
10	ControlPan	
11	ControlExpressionController	
12	ControlEffectControl1	Guitar
13	ControlEffectControl2	Key
14	ControlUndefined14	Style
15	ControlUndefined15	Swing
16	ControlGeneralPurpose1	Feel
17	ControlGeneralPurpose2	Latch On/Off
18	ControlGeneralPurpose3	Doubling On/Off
19	ControlGeneralPurpose4	Drop D On/Off
20	ControlUndefined20	Amp
21	ControlUndefined21	Crunch
22	ControlUndefined22	Delay
23	ControlUndefined23	Rate
24	ControlUndefined24	Chorus
25	ControlUndefined25	Reverb
26	ControlUndefined26	
27	ControlUndefined27	
28	ControlUndefined28	
29	ControlUndefined29	
30	ControlUndefined30	
31	ControlUndefined31	
32	ControlSB0 (Bank select)	
33	ControlSB1 (ModWheel)	
34	ControlSB2 (Breath)	
35	ControlSB3 (Undefined)	
36	ControlSB4 (Foot controller)	
37	ControlSB5 (Portamento time)	
38	ControlSB6 (DataEntry LSB)	
39	ControlSB7 (Channel Volume)	
40	ControlSB8 (Balance)	
41	ControlSB9 (Undefined)	
42	ControlSB10 (Pan)	
43	ControlSB11 (Expression)	
44	ControlSB12 (Effect control 1)	
45	ControlSB13 (Effect control 2)	
46	ControlSB14 (Undefined)	
47	ControlSB15 (Undefined)	
48	ControlSB16 (General purpose 1)	
49	ControlSB17 (General purpose 2)	
50	ControlSB18 (General purpose 3)	
51	ControlSB19 (General purpose 4)	
52	ControlSB20 (Undefined)	
53	ControlSB21 (Undefined)	
54	ControlSB22 (Undefined)	
55	ControlSB23 (Undefined)	
56	ControlSB24 (Undefined)	
57	ControlSB25 (Undefined)	
58	ControlSB26 (Undefined)	
59	ControlSB27 (Undefined)	
60	ControlSB28 (Undefined)	
61	ControlSB29 (Undefined)	
62	ControlSB30 (Undefined)	
63	ControlSB31 (Undefined)	
64	ControlDampPedal (Sustain)	
65	ControlPortamentoOnOff	
66	ControlSostenuto	
67	ControlSoftPedal	
68	ControlLegatoFootSwitch	
69	ControlHold2	
70	ControlSoundController1 (Sound Variation)	
71	ControlSoundController2 (Harmonic Intensity)	
72	ControlSoundController3 (Release time)	
73	ControlSoundController4 (Attack time)	
74	ControlSoundController5 (Brightness)	
75	ControlSoundController6	
76	ControlSoundController7	
77	ControlSoundController8	
78	ControlSoundController9	
79	ControlSoundController10	
80	ControlGeneralPurposeController5	
81	ControlGeneralPurposeController6	
82	ControlGeneralPurposeController7	
83	ControlGeneralPurposeController8	
84	ControlPortamentoControl	
85	ControlUndefined85	
86	ControlUndefined86	
87	ControlUndefined87	
88	ControlUndefined88	
89	ControlUndefined89	
90	ControlUndefined90	
91	ControlEffects1Depth	
92	ControlEffects2Depth	
93	ControlEffects3Depth	
94	ControlEffects4Depth	
95	ControlEffects5Depth	
96	ControlDataIncrement	
97	ControlDataDecrement	
98	ControlNonRegisteredParameterNumberLSB	
99	ControlNonRegisteredParameterNumberMSB	
100	ControlRegisteredParameterNumberLSB	
101	ControlRegisteredParameterNumberMSB	
102	ControlUndefined102	
103	ControlUndefined103	
104	ControlUndefined104	
105	ControlUndefined105	
106	ControlUndefined106	
107	ControlUndefined107	
108	ControlUndefined108	
109	ControlUndefined109	
110	ControlUndefined110	
111	ControlUndefined111	
112	ControlUndefined112	
113	ControlUndefined113	
114	ControlUndefined114	
115	ControlUndefined115	
116	ControlUndefined116	
117	ControlUndefined117	
118	ControlUndefined118	
119	ControlUndefined119	
120	ControlReservedForChannelModeMessages120	
121	ControlReservedForChannelModeMessages121	
122	ControlReservedForChannelModeMessages122	
123	ControlReservedForChannelModeMessages123	
124	ControlReservedForChannelModeMessages124	
125	ControlReservedForChannelModeMessages125	
126	ControlReservedForChannelModeMessages126	
127	ControlReservedForChannelModeMessages127	

